



# MobiONE Quick Start Guide

- 1** Sign up and then log in to <https://www.mobi-server.com/> and download/install **MobiONE**. Reboot your PC when complete.
- 2** Log in to **MobiONE** using your credentials found in the **MobiCode** Portal. Click "**Save Login**" to complete.
- 3** Configure the ports by going to Settings () , "**Port Configuration**" and click "**Start Configuration**".
- 4** Connect a data cable to a device and then to each port you will be using. You can use the same device for each port. Click "**Stop Configuration**" to complete.
- 5** You can change your settings in the "**Erasure Settings**" tab.
- 6** Check that **MobiONE** install is set to **YES** in the "**MobiONE**" tab.
- 7** When you are happy with your settings click back on the **WIPE** tab (). You should see a square white tile for each of your configured ports.
- 8** Now connect a device. Depending on your settings, a **MobiCHECK** will run and then the testing app will install on the device. The boxes at the top of the tile will fill to reflect this.
- 9** Now you are ready to **TEST!** Once testing is complete, the results will upload automatically. If you have disconnected the device, you will be prompted to reconnect to upload the results.
- 10** Now the results have been saved, you are ready to **WIPE** the device. Simply click '**Start**' on the blue tile to commence the **WIPE** process.